



Assa Abloy - Authoring Guide

Component – Experience Fragment

Version #	Contributor	Date	Description	Reviewed By
0.1	Rajen Upreti	10 Jan 2022	Initial version	

Table of Contents

1 Overview	4
2 Business Use Case	4
3 Design.....	4
4 Authoring Steps.....	4
5 User Interface.....	13

Component: Experience Fragment

1 Overview

The Experience Fragment allows to create and maintain standard predefined section throughout the site we are designing. Here we can configure the header, footer, menu item, logo, and any other items which need to be placed in the page for the whole site/pages.

2 Business Use Case


Experience Fragment is useful when we need to display a constant experience of items throughout the site as standard.

3 Design


This component contains the authoring for other components. Both header and footer part of the experience section needs to be created individually.

4 Authoring Steps


- **Step 1:** Create a new Experience Fragment, go to the AEM window and select the section Experience Fragment as below.




- **Step 2:** Go to the required brand and folder for which experience fragment needs to be created and click Create.



- **Step 3:** Select the option Experience Fragment from the list.





- **Step 4:** Select the required template for the fragment and click Next.




5 Header Authoring

- **Step 1:** Enter the suitable name as Header Experience Fragment as required and click Create.








- **Step 2:** Open the page for the configuration. Or click Done and select the page and click Edit to open the page for configuration.




- **Step 3:** Once the Page is opened, go to the content panel from the top left side panel and then click on the component tab and drag the Header from the left side panel and drop it inside the Layout Container.



Or choose it from the available component list.





- **Step 4:** Select the Header component added to the page and configure the same for all the required items for header. Add and configure all the other components required for Header part like: Logo, Icon Group, Global Search, Mega menu and User Account, etc
- For the configuration of the Header and other components, please refer the authoring guide for the same.




6 Footer Authoring


- **Step 1:** Enter the suitable name as Footer Experience Fragment as required and click Create.



- **Step 2:** Open the page for the configuration. Or click Done and select the page and click Edit to open the page for configuration.



- **Step 3:** Once the Page is opened, go to the content panel from the top left side panel and then click on the component tab and drag the Footer from the left side panel and drop it inside the Layout Container.



Or choose it from the available component list.




- **Step 4:** Select the Footer component added to the page and configure the same for all the required items for header. Add and configure all the other sections required for Footer part like footer links, copyright and other required sections.
- For the configuration of the Footer, please refer the authoring guide for the same.


7 Page configuration for Experience Fragment.

Authors need to select the required experience fragment while configuring the page template so that every time any page is created using that page template, the Experience Fragment is automatically considered for that page.




- **Step 1:** To configure the page template, go to the AEM main page and select the Hammer icon (Tools) in the top left section.




- **Step 2:** Go inside the template, select the required folder, and create new/edit and existing template.




- **Step 3:** Edit the required Header / Footer section and select the required path of the Experience fragment for Header and Footer and click Done.



- **Step 4:** Header and footer can also be configured for the page template dynamically by configuring the Experience Fragment path in the site level configuration.
- To configure Site Level Configuration, go to AEM, select and Edit the site level configuration.




- Select Per Brand/Site specific configurations and



- Select the path in the page template (Follow step 3 of above [section 7](#) for page template create/update)

- Select “Select Site Level Config XF” as Header or Footer section in the page template. Priority is always given to the Experience fragment path added in the Site level but if there is no value available in the Site Level Configuration for Header and Footer, the page will take the path entered in the Variation section.



Once the page template is configured for the Experience Fragment, all the pages created using that page will consider the Experience Fragment configured.

8 User Interface

